

## 1 Mouse Scroll Wheel

With the latest versions of **Chrome**, **Microsoft Edge** and **FireFox** you will find the mouse wheel scrolls the page, not the tuning scale, to overcome this hold the “Shift” key down while using the mouse wheel, you will now be able to tune using the mouse wheel.

## Internet Browse audio issues (no sound)


### 2 No Sound Chrome

The latest version of Chrome has once again caused issues with sound on Websdr’s

To resolve the problem you need to go to **Site settings** and change the way Chrome handles sound.


Open up a WEBSDR:-

Press “Site information”




This will take you to this pop up:-

Select Site settings



In the site settings page scroll down to sound option



Select sound option →



From the drop down menu select “Allow” then close the page.


Refresh the Websdr page, you should now have sound, you will have to run this procedure for any new WEBSDR site you open.

### 3. No sound **Firefox**







The latest version 103 of Firefox defaults to no sound.

- General
- Home
- Search
- Privacy & Security
- Sync
- More from Mozilla

Go to “Firefox settings, select “Privacy and Security”

Scroll down to “Permissions” and select  Autoplay settings

### Permissions

 Location	Settings...
 Camera	Settings...
 Microphone	Settings...
 Notifications <a href="#">Learn more</a>	Settings...
<input type="checkbox"/> Pause notifications until Firefox restarts	
 Autoplay	Settings...
 Virtual Reality	Settings...
<input checked="" type="checkbox"/> Block pop-up windows	Exceptions...
<input checked="" type="checkbox"/> Warn you when web sites try to install add-ons	Exceptions...

Select “Allow Audio and Video” then save settings

Settings - Autoplay ✕


Default for all web sites: **Allow Audio and Video** ▾

You can manage the sites **Allow Audio and Video** play settings here.


Web Site	Status
----------	--------

#### 4. No sound on **Microsoft Edge**

Go to Browser setting option (Alt+F)




select settings




From the menu

“Select Cookies and site permissions”



Scroll down to **Media autoplay** and select



From the drop down option select “Allow”